

There are 2 types of G081 printers... TN3270 Printers and IP printers.

- a. TN3270 printers go thru a Rumba print session on a PC and can be set up to print to a file or print to a physical printer.
- b. IP printers go directly to a network printer through an IP address already designated.

SETTING UP YOUR TN3270 RUMBA MAINFRAME PRINTER SESSION

STEP 1: Open the Rumba Mainframe Printer Application

- a. Click on "Start" button (in lower left of screen).
- b. Click on "Programs"
- c. Click on "RUMBA 2000 Folder"
- d. Click on "Mainframe Printer"

STEP 2: Configure your mainframe connection.

- a. Click on "Connection" from the top menu.
- b. Click on "Configure"; a pop-up window will appear. See Figure 1.

STEP 3: Under the "General" tab check/choose the following options; also Figure 1.

- a. Auto Connection Option = Auto Connect
- b. Installed Interface = TN3270




Figure 1.

STEP 4: Under the "TN3270" tab, make the following changes; see Figure 2.

- a. Insert the correct IP address in the "Destination Name/Address"
 - 1) Click on the "INSERT" button; a new box will pop up.
 - 2) Enter comm1.okc.disa.mil Click "OK".
- b. Enter the G081 Printer ID that you wish to use in the "DEVICE NAME".
- c. Check "AUTO RECONNECT SESSION"
- d. Click "OK" to close the "Connection Configuration" window.




Figure 2.

STEP 5A: Directing Rumba output to a **physical printer**.

- a. Choose "File" from the menu and then click on "Page Setup". A pop-up box will appear.
 - 1) Under the "General" tab--
 - A. In "Printer name", select the printer you wish to print to.
 - B. Set "Formatting overrides" to "Use all formatting specified by host"
 - 2) Under the "Scaling" tab; (If the 'Paper', 'Layout' and 'Scaling' are shaded gray and can't be changed then go to the 'Direct Printing' tab and uncheck the Direct Printing)
 - A. Chose "Scale host page within top and bottom margins" in length option.
 - B. Choose "Scale host page within left and right margins" in width option.
 - 3) Under the "Layout" tab
 - A. Set lines per page to 88
 - B. Set characters per line to 132
 - C. Set lines per inch to 8
 - 4) Under the "Job Control" tab
 - A. Check "Printer sharing" under "Job control"
 - B. Set "Feed" to "standard form feed"
 - 5) Under the "Direct Printing" tab
 - A. **Un**check "direct printing"


Continue to STEP 6.

STEP 5B: Directing Rumba output to a **file**

- a. Ensure a "text" or a "print-to-file" printer is set up on the PC.
 - 1) Click on "START", then "Settings" and then "Add printer"; the 'add printer wizard' will step you through the process.
 - 2) Choose 'My computer'
 - 3) Check the 'FILE' port
 - 4) Choose 'Generic' and 'Generic/text only'
 - 5) Go to 'File', 'Page Setup'
 - 6) Select 'Keep existing driver'
 - 7) Change the printer name if you want or just leave it as 'Generic/text only'
 - 8) Select "Not Shared"
- b. In the Rumba Mainframe Printer session, go to 'File', 'Page Setup'
 - 1) Under the "General" tab
 - A. In the "Printer Name" select the text printer just created above.
 - B. Set "Formatting overrides" to "use all formatting specified by host"
 - 2) The 'Paper', 'Layout' and 'Scaling' tabs are shaded gray and need not be changed.
 - 3) Under the "Job control" tab
 - A. Set "Feed" to "standard form feed"
 - B. Set "Generate unique file name" to checked or leave it unchecked if you want the file to be overwritten every time.
 - C. Set the "base file name" to the directory and name of your choosing, i.e. "d:\reports\vtap007\print.txt". You must specify the file and the extension.
 - 4) Under the "Direct Printing" tab
 - A. Check "direct printing" on.

STEP 6: Font Mapping –(your print session must be disconnected or holding print for this to work)

Click on this button for Font Mapping...



- a. Font mapping— (suggested, but may be changed)
 - font id = default
 - font = Courier New
 - font style = host
 - font size = 7

All requests to get a G081 printer ID set up or changed go through Perry Elder at Scott AFB perry.elder@scott.af.mil. If you have questions or problems contact the FAO g081fao@okc.disa.mil